

Title:	How to Upgrade Temperature Screening Terminal	Version:	v1.0	Date:	5/13/2020
Product:	Access Control	Page:	1 of 4		

How to Upgrade Temperature Screening Terminal

Steps

1. Upgrade main firmware.

The screenshot shows the device's web interface with the 'System Maintenance' menu item highlighted in red. A file selection dialog is open, showing the file 'ACS_671_AI3_EN_GM_V2.2.6_build200430.zip' selected. The 'Upgrade' section shows 'Access Controller' selected in the 'Select Type' dropdown.

2. Upgrade extension firmware.

The screenshot shows the device's web interface with the 'System Maintenance' menu item highlighted in red. A file selection dialog is open, showing the file 'ACS_DS-K1T671_ST1_GML_GM_V1.0.1_build200327_Net.bin' selected. The 'Upgrade' section shows 'Extension Module' selected in the 'Select Type' dropdown and '1' selected in the 'Extension Module No.' dropdown.

Title:	How to Upgrade Temperature Screening Terminal	Version:	v1.0	Date:	5/13/2020
Product:	Access Conrtol	Page:	2 of 4		

3. Upgrade thermal module firmware.

The screenshot displays the Hikvision web management interface for a device. The top navigation bar includes tabs for Name, Connection, Network Parameters, Device Type, Serial No., Security Level, Resource Usage, Firmware Upgrade, and Operation. The device status is shown as 'Online' with 'No available version' for the current firmware.

In the left sidebar, the 'System Maintenance' option is highlighted with a red box. Below it, various system settings like RS-485, Security, Network, Alarm, and Status are listed.

A file selection dialog box is open, showing a directory structure. The file 'digicap_thermo-en-gm' is selected and highlighted with a red box. Other files in the list include ACS_671_AI3_EN_GM_V2.2.6_build200430.zip, ACS_DS-K1T671_ST1_GML_GM_V1.0.1_build200327_Net.bin, digicap.dav, digicap_thermo-EN-build200506.rar, and read me.txt.

Below the dialog, the 'Upgrade' section is visible. The 'Select Type' dropdown menu is set to 'Access Controller' and is highlighted with a red box. There are also 'File', 'Browse', and 'Upgrade' buttons.

Title:	How to Upgrade Temperature Screening Terminal	Version:	v1.0	Date:	5/13/2020
Product:	Access Conrtol	Page:	3 of 4		



See Far, Go Further
***HIK*VISION Technical Support**